

Control your GoStream Devices by Computer Software or Bitfocus Companion.


Control by Computer Software

1. Update your GoStream device to the latest version. Download the computer software - GoStream and install it to your PC (both Mac and Windows are supported).
2. Connect your device and PC. There are 2 connection methods, one is through USB connection, and the other is through network IP connection.

Method 1: Connect through USB

①Connect your PC with GoStream USB 1 port through a USB cable. The software and GoStream device are automatically connected.

②In this way, you can only connect up to one device at a time.




Method 2: Connect through IP Internet

①Connect your GoStream device and PC into a network.

②In the GoStream software, click 'File', then click 'Connect' item. You can see your GoStream device in the Network list. Click it and connect it.


③Of course, you can also connect by manually entering your IP address.

④In this connection way, you can connect multiple devices and switch between them.



Control by Bitfoucs Companion

1. Update your GoStream device to the latest version. Download and install the Companion software.
2. Download 'companion-module-osee-gostream' and extract this file into the following directory:
Companion > resources > bundled-modules
3. Connect your GoStream device and PC into a network.
4. Open the Companion. In the 'Add connection' item, search 'gostream' and click 'Add'.
5. Change the IP address. You can search your GoStream device's IP address in ' Menu > setting > network'.



通过电脑软件和Companion软件来控制你的GoStream切换台


由电脑软件GoStream控制

1. 升级你的GoStream切换台设备到最新的固件版本。下载并安装GoStream电脑软件，Mac和Windows电脑分别下载对应版本。
2. 连接你的GoStream切换台设备与电脑。有两种连接模式，其一是通过USB直接连接，二是通过IP网络进行连接。

方法1：通过USB线进行连接

①连接你的电脑与GoStream切换台设备的USB1接口。之后GoStream软件会自动与设备进行连接。

②在这种连接方法下，一台电脑一次最多只能连接一台设备。




方法2：通过IP网络连接

①将你的GoStream切换台设备与你的电脑连接到同一个IP地址下。

②打开GoStream电脑软件，点击左上角的'File'，然后点击'Connect'。在新弹窗中，你可以看到你的GoStream切换台设备在网络列表中。选择后连接即可。

③当然你也可以通过手动输入IP地址来进行连接。

④在这种连接方式下，你可以同时连接多个设备进入网络。



由Bitfoucs Companion控制

1. 升级你的GoStream切换台设备到最新的固件版本。下载并安装Companion到你的电脑。
2. 下载 'companion-module-osee-gostream' 文件并将其解压到如下路径：
Companion > resources > bundled-modules
3. 将你的GoStream切换台设备与你的电脑接入同一网络。
4. 打开Companion。添加'gostream'设备。
5. 修改连接的IP地址。你可以通过如下切换台菜单路径来确认GoStream切换台设备的IP地址：
Menu > setting > network



GoStreamデバイスをコンピューターソフトウェアやBitfocus Companionで制御します


コンピューターソフトウェアによる制御

1. GoStreamデバイスを最新バージョンにアップデートしてください。コンピューターソフトウェアであるGoStreamをダウンロードし、PCにインストールしてください（MacとWindowsの両方に対応しています）。
2. ネットワークとPCを接続してください。接続方法は2つあります。1つはUSB接続で、もう1つはネットワークIP接続です。

方法1：USB経由で接続

①USBケーブルを使用して、PCをGoStreamのUSB 1ポートに接続します。ソフトウェアとGoStreamデバイスが自動的に接続されます。

②この方法では、一度に1台のデバイスしか接続できません。




方法2：IPインターネット経由で接続

①GoStreamデバイスとPCをネットワークに接続します。

②GoStreamソフトウェアで、「ファイル」をクリックし、次に「接続」項目をクリックします。ネットワークリストにGoStreamデバイスが表示されますので、それをクリックして接続します。

③もちろん、IPアドレスを手動で入力して接続することもできます。

④この接続方法では、複数のデバイスを接続し、それらを切り替えることができます。



Bitfocus Companion)による制御

1. GoStreamデバイスを最新バージョンにアップデートしてください。Companionソフトウェアをダウンロードしてインストールしてください。
2. 以下のディレクトリに 'companion-module-osee-gostream' をダウンロードし、ファイルを抽出してください。：
Companion > resources > bundled-modules
3. GoStreamデバイスとPCをネットワークに接続してください。
4. Companionを開いてください。'接続の追加'項目で'gostream'を検索し、'追加'をクリックしてください。
5. IPアドレスを変更してください。GoStreamデバイスのIPアドレスは、'メニュー>設定>ネットワーク'で検索できます。

